

Game Controller Element Numbers for SuperCollider HID				
	Sony DualShock (PS4)	Sony DualSense (PS5)	Logitech FA310 Mode D	Microsoft XBox
Connection type	Bluetooth	Bluetooth	USB	Bluetooth
HID ID	ID (1356, 2508)	ID (1356, 3302)	ID (1133,49686)	ID (1118, 765)
Control Surface [sony   xbox]	Element#, (value range)	Element#, (value range)	Element#, (value range)	Element#, (value range)
<i>Square</i>   <i>X</i>	0, (0 or 1)	0, (0 or 1)	0, (0 or 1)	13, (0 or 1)
<i>X</i>   <i>A</i>	1, (0 or 1)	1, (0 or 1)	1, (0 or 1)	10, (0 or 1)
<i>O</i>   <i>B</i>	2, (0 or 1)	2, (0 or 1)	2, (0 or 1)	11, (0 or 1)
<i>Triangle</i>   <i>Y</i>	3, (0 or 1)	3, (0 or 1)	3, (0 or 1)	14, (0 or 1)
<i>L1</i>   <i>LB</i>	4, (0 or 1)	4, (0 or 1)	4, (0 or 1)	16, (0 or 1)
<i>R1</i>   <i>RB</i>	5, (0 or 1)	5, (0 or 1)	5, (0 or 1)	17, (0 or 1)
<i>L2</i>   <i>LT button</i>	6, (0 or 1)	6, (0 or 1)	6, (0 or 1)	not found yet
<i>R2</i>   <i>RT button</i>	7, (0 or 1)	7, (0 or 1)	7, (0 or 1)	not found yet
<i>Share</i>   <i>Back</i>	8, (0 or 1)	8, (0 or 1)	8, (0 or 1)	25, (0 or 1)
<i>Options</i>   <i>Start</i>	9, (0 or 1)	9, (0 or 1)	9, (0 or 1)	21, (0 or 1)
<i>L3</i>   <i>LSB button</i>	10, (0 or 1)	10, (0 or 1)	10, (0 or 1)	not found yet
<i>R3</i>   <i>RSB button</i>	11, (0 or 1)	11, (0 or 1)	11, (0 or 1)	not found yet
<i>Logo</i>	12, (0 or 1)	12, (0 or 1)	not found yet	not found yet
<i>Trackpad button</i>	13, (0 or 1)	13, (0 or 1)	N/A	N/A
<i>L3</i>   <i>LSB x-axis</i>	14, (0 to 255)	14, (0 to 255)	13, (0 to 255)	0, (0-65535)
<i>L3</i>   <i>LSB y-axis</i>	15, (0 to 255)	15, (0 to 255)	14, (0 to 255)	1, (0-65535)
<i>R3</i>   <i>RSB x-axis</i>	16, (0 to 255)	16, (0 to 255)	15, (0 to 255)	2, (0-65535)
<i>R3</i>   <i>RSB y-axis</i>	17, (0 to 255)	17, (0 to 255)	16, (0 to 255)	3, (0-65535)
<i>L2</i>   <i>LT continuous</i>	19, (0 to 255)	19, (0 to 255)	not found yet	26, (0-1023)
<i>R2</i>   <i>RT continuous</i>	20, (0 to 255)	20, (0 to 255)	not found yet	27, (0-1023)
<i>up</i>	18, (0)	18, (0)	17, (0)	28, (1)
<i>up+right</i>	18, (1)	18, (1)	17, (1)	28, (2)
<i>right</i>	18, (2)	18, (2)	17, (2)	28, (3)
<i>right+down</i>	18, (3)	18, (3)	17, (3)	28, (4)
<i>down</i>	18, (4)	18, (4)	17, (4)	28, (5)
<i>down+left</i>	18, (5)	18, (5)	17, (5)	28, (6)
<i>left</i>	18, (6)	18, (6)	17, (6)	28, (7)
<i>left+up</i>	18, (7)	18, (7)	17, (7)	28, (8)
<i>release</i>	18, (8)	18, (8)	17, (8)	28, (0)